| Category | Command name | Command syntax | Description |
|-------------|--------------------------|---------------------|---|
| Basic | LED state | EC,L,%s | Turn LED on or off or check state. 1=on, 0=off, ?=check |
| Basic | Find blink | EC,FIND | Cause white LED to blink rapidly. Any following command will terminate find mode. |
| Basic | Name probe circuit | EC,NAME,%s | Name the device. Any string up to 16 ASCII characters. ?=check name |
| Basic | Get info | EC,I | Get device information. Returns deviceType,firmwareVersion |
| Basic | Get status | EC,STATUS | Read device status. Returns reason for last restart (P=powered off, S=software reset, B=brown out, W=watchdog, U=unknown), and voltage at Vcc pin |
| Basic | Set baud | EC,BAUD,%s | Change baud rate. N=baud rate, ?=check baud rate |
| Basic | Lock protocol | EC,PLOCK,%s | Lock/unlock communications protocol. 1=Lock protocol, 0=unlock protocol, ?=check protocol lock state |
| Basic | Factory reset | EC,FACTORY | Factory reset. Clears calibration, LED settings |
| Basic | LED state | TEMP,L,%s | Turn LED on or off or check state. 1=on, 0=off, ?=check |
| Basic | Find blink | TEMP,FIND | Cause white LED to blink rapidly. Any following command will terminate find mode. |
| Basic | Name probe circuit | TEMP,NAME,%s | Name the device. Any string up to 16 ASCII characters. ?=check name |
| Basic | Get info | TEMP,I | Get device information. Returns deviceType, firmwareVersion |
| Basic | Get status | TEMP,STATUS | Read device status. Returns reason for last restart (P=powered off, S=software reset, B=brown out, W=watchdog, U=unknown), and voltage at Vcc pin |
| Basic | Set baud | TEMP,BAUD,%s | Change baud rate. N=baud rate, ?=check baud rate |
| Basic | Lock protocol | TEMP,PLOCK,%s | Lock/unlock communications protocol. 1=Lock protocol, 0=unlock protocol, ?=check protocol lock state |
| Basic | Factory reset | TEMP,FACTORY | Factory reset. Clears calibration, LED settings |
| Calibration | Calibrate sensor | EC,CAL,%s,%s | Calibrate sensor. Step 1: dry, step 2: low,N (N=conductivity), step3: high,N. Also, ?=check calibration, clear=delete calibration, N=single point calibration |
| Calibration | Export calibration | EC,EXPORT,%s | Export calibration. no param=export, ?=check data size of calibration export data |
| Calibration | Import calibration | EC,IMPORT,%s | Import calibration. To correctly import, must repeat this command enough times to send all the calibration strings in. Example: 65 20 61 20 63 6F |
| Calibration | Set temp comp | EC,T,%s | Set the temperature compensation value. Must be reset after power loss. N=temperature in celsius, ?=current temp compensation value |
| Calibration | Set temp comp+read | EC,RT,%s | Set the temperature compensation value then take a reading. Must be reset after power loss. N=temperature in celsius, ?=current temp compensation value |
| Calibration | Calibrate sensor | TEMP,CAL,%s | Calibrate sensor. t=any temperature, clear=delete calibration, ?=check if calibrated |
| Calibration | Export calibration | TEMP,EXPORT,%s | Export calibration. no param=export, ?=check data size of calibration export data |
| Calibration | Import calibration | TEMP,IMPORT,%s | Import calibration. To correctly import, must repeat this command enough times to send all the calibration strings in. Example: 65 20 61 20 63 6F |
| Logfile | Get SD card data | ARD,DUMPDATA,%s | Tell arduino to dump last N lines of data stored on the SD card to the serial port. Leave N blank for all data. |
| Logfile | Clear SD card data | ARD,CLEARDATA,%s | CAREFUL! DATA LOSS! Tell arduino to clear all but the last N lines of data stored on the SD card. Leave N blank to clear all data. |
| Logfile | Start new log file | ARD,STARTFILE,%s | Start new log file on SD card by archiving old file. Argument is name to use to archive old file. |
| Logfile | Log note | ARD,NOTE,%s | Log a note in the datafile. Argument is the text of the note. |
| | t Cont. meas. | EC,C,%s | Continuous reading mode. N=one reading every N seconds(1-99), 0=disable, ?=check |
| | t Single measurement | EC,R | Take a single reading |
| | t Cont. meas. | TEMP,C,%s | Continuous reading mode. N=one reading every N seconds(1-99), 0=disable, ?=check |
| | t Single measurement | TEMP,R | Take a single reading |
| | t Cont. meas. mode | ARD,C,%s | Change continuous measurement state. 0=no continuous measuring, N=measurement every N milliseconds, ?=check continuous measurement state |
| | t Single shot mode | ARD,SSM,%s | Change single shot measurement mode - boot, measure, signal ready for power down. 0=off, 1=on, ?=check single shot mode |
| | t Measure and log | ARD,M | Take a full measurement and log to the data file. |
| | t Take sample | SAMP,SAMPLE,%s | Take a water sample if argument is 1. 0=reset sample record ?=has sample been retrieved? |
| Memory | Enable data logger | TEMP,D,%s | Enable/disable data logger and set logging interval. n=log every nx10 seconds, 0=disable, ?=Check current data logging status/interval |
| Memory | Memory recall | TEMP,M,%s | Recall logged readings. No param=last stored reading, all=all readings in CSV string, ?=memory location of last stored reading, clear=clear all stored memory |
| Mode | Set probe type | EC,K,%s | Set the probe type to match connected probe. N=probe type (0.1, 1.0, or 10), ?=check set probe type |
| Mode | Enable meas. outputs | EC,O,%s,%s | Enable/disable measurement outputs. EC,N=conductivity enable(1)/disable(0), similarly for TDS (total dissolved solids), S (salinity), SG (specific gravity), and ?=check enable status |
| Mode | Response mode | EC,*OK,%s | Response code mode. 1=enable response, 0=disable response, ?=check response code mode |
| Mode | Sleep mode | EC,SLEEP | Enter low power sleep mode. Any command will wake. Standby = 18 mA, sleep = 0.7 mA |
| Mode | I2C protocol | EC,I2C,%s | Change to I2C communication protocol and reboot. N=I2C address |
| Mode | Set temp scale | TEMP,S,%s | Set temperature scale. c=celsius, k=kelvin, f=fahrenheit, ?=check current temperature scale |
| Mode | Response mode | TEMP,*OK,%s | Response code mode. 1=enable response, 0=disable response, ?=check response code mode |
| Mode | Sleep mode | TEMP,SLEEP | Enter low power sleep mode. Any command will wake. Standby = 15.4 mA, sleep = 0.4 mA |
| Mode | I2C protocol | TEMP,I2C,%s | Change to I2C communication protocol and reboot. N=I2C address |
| Mode | EC probe sleep | ARD,EC_SLEEP | Tell the EC probe to go to sleep, for power savings. Send any command to the EC probe to wake it again. |
| Mode | TEMP probe sleep | ARD,TEMP_SLEEP | Tell the TEMP probe to go to sleep, for power savings. Send any command to the TEMP probe to wake it again. |
| Mode | Arduino sleep mode | ARD,ARD_SLEEP,%s | Set or check arduino sleep mode. 1=on, 0=off, ?=check |
| Mode | Signal for power down | ARD,PWRDOWN | Signal |
| Mode | Restore default settings | | Restore default settings. This will set current settings to default, and will update settings file on disk to defaults. |
| Mode | Print current settings | ARD,PRINTSETTINGS | Print current settings to serial port. |
| Mode | Control sample valve | SAMP,VALVE,%s | Open or close sample valve. 1=open, 0=close |
| Status | Connection status | ARD,CONNECT,%s,%s | Get or check connection status. First arg is EC/TEMP/SD to check conductivity probe / temp probe / SD card, second argument is CONNECT/DISCONNECT/? to connect, disconnect, or check connection status |
| Time | Get millis | ARD,MILLIS | Get current value of Arduino millisecond timer |
| | Timestamp | ARD.TIMESTAMP.%s.%s | Adjust or check arduino time. Arduino keeps track of real time using embedded RTC on datalogger shield. ?=check current arduino time S=set time with argument YEAR,MONTH,DAY,HOUR,MIN,SEC |
| Time | rimestamp | ,,,,,,,,, | raject of electrical and the radiation feels and the end additional |